

VoiceQ Pro & Pro Tools Integration: User Guide

## **VoiceQ and Digital Audio Workstations**

This guide describes the configurations and procedures used within VoiceQ and Digital Audio Workstations and are intended for use by Audio Engineers to understand the operation and configuration of both systems.

During the recording process VoiceQ takes over the role of playing back the movie file from Pro Tools. You can leave the movie file loaded in your Pro Tools session, but the track should be disabled, to avoid competing with the VoiceQ Application.

VoiceQ superimposes the scrolling text on the movie and outputs it via the second DVI port of your Apple Mac video card (or the external DVI port on laptops). VoiceQ uses the Graphics Processing Unit (GPU) and the Memory on the video card to process the video, which reduces the load on the CPU of your computer.

VoiceQ will chase and scrub with Pro Tools while you work in Pro Tools. VoiceQ also has an option to cue Pro Tools when you select a line in VoiceQ. This will locate the Pro Tools session to the record location for the selected line with an adjustable pre-roll value.

Recent improvements specific to VoiceQ Pro:

GENMTC Support for accurate sync
VoiceQ listens for 'Start, Continue, Play & Stop commands'
Latency Compensate – Is now redundant with GENMTC active. We
have left it in as a feature for hardware that may have trouble
performing under load.
Postroll – Users can set post-roll in VoiceQ Preferences
Mute Sound when Recording – mutes VoiceQ audio when recording
Recording starts before a set time (See Preferences)
Recording Icon added to VoiceQ Transport

Actual recording of audio and management of playlists still takes place in Pro Tools using your normal process.

Note: In a single computer configuration VoiceQ will work with many other recording applications including Logic Pro and others. Check our website for the correct set up instructions and screen shots for these applications.

Note: In a dual computer configuration the Digital Audio Workstation may be any device that will output MIDI Time Code (MTC) and/or MIDI Machine Control.

#### **DAW Preferences**



The preferences have been slightly altered to allow easier user access to options for MIDI.

**MIDI/Rewire Option Selection –** Allows users to select either MIDI or ReWire connections. *Note: ReWire will not be visible if not active or installed.* 

**Output MMC Port Checkbox –** Outputs MIDI/ReWire data and ignores any chase data sent from Pro Tools. This option is used if Pro Tools engineers need to make changes on the fly and not affect VoiceQ playback.

MIDI Selection - This dropdown lists all available external connections

**Latency Compensate –** If playback is incorrect between VoiceQ and the set DAW. Users can adjust the latency using the slider.

**Pre-Roll** – Users can now set pre-roll in Pro Tools and leave this option unchecked. This option is available if users wish to see pre-roll when not connected to a DAW

**Postroll –** Sets the time the DAW records after the line is completed

Mute Sound when recording - Mutes VoiceQ audio

**Recording Starts before –** Sets the time the DAW records before the line begins.

## Single Machine Setup (using IAC driver)


The Apple Inter Application Communication (IAC) Bus is used to send all MIDI information when VoiceQ and Pro Tools are on the same computer – we refer to this as a **Single Computer Configuration**.

A MIDI interface or Network Session is used when the Digital Audio Workstation (DAW), in this case Pro Tools, and VoiceQ are on separate machines (dual computer configuration). If you are using a **Dual Computer Configuration** you do not need the IAC Bus and can skip directly to the next section.

 Open MIDI Studio. It is located in Applications/Utilities/Audio MIDI Setup.app. Launch this app and select Window>Show MIDI Window (Command + 2) from the menu to open it.




2. **Select IAC Driver**. Double click it to open the IAC Driver Properties window.




- 3. Add Ports by **selecting '+' button** and **give the port a name**. In this example, we named it **VoiceQ MMC/MTC**.
- 4. Click the checkbox 'Device is online' to enable this virtual MIDI device.

- 5. Launch Pro Tools application and select Pro Tools>Preferences... from the menu.
- Go to Synchronization tab and check both 'Machine Chases Memory Location' and 'Machine Follows Edit Insertion/Scrub' checkboxes.



- 7. **Select Setup>Peripherals...** from the menu to open the peripherals setup window.
- 8. **Go to Synchronization tab** and **Select the IAC Driver** added in Step 3 for MTC Reader and Generator ports. In this example, it is named: IAC Driver, VQ & PT.



9. Go to Machine Control tab and enable both Master and Slave, select the IAC Driver under the Master, and give the Master's ID = 120 so as not to cause a conflict when you Set ID of the Slave to 127.




10. Select Setup>MIDI>MIDI Beat Clock... from the Pro Tools main menu to open the MIDI Beat Clock window. Enable MIDI Beat Clock and select the IAC Driver.




11. In the **Transport window or Synchronizations options** via transport, select '**GEN MTC**'.



12. Launch VoiceQ and select VoiceQ>Preferences... from VoiceQ main menu.



- 13. **Enable Output MMC Port** and **select the IAC Driver** by name. In this example it is VoiceQ MMC.MTC.
- 14. Select the **MIDI Chase Icon** in the lower left hand corner of the VoiceQ Project window.



VoiceQ and Pro Tools are now ready to communicate through a virtual MIDI device.


### **Dual Machine Setup using Network (RTC-MIDI)**

The Dual Computer Configuration is when Pro Tools and VoiceQ are on separate computers with MIDI information sent via the Local Area Network (LAN).


With a **Dual Computer Configuration**, we can use Apple's MIDI network feature to send MIDI via the Local Area Network. This setup does not require any additional MIDI hardware. First configure your LAN (if required) so the 2 machines can communicate and 'see' each other on the local network. Contact your Systems Administrator for assistance if required.

#### On the Mac running Pro Tools

 Open MIDI Studio. It is located in Applications/Utilities/Audio MIDI Setup.app. Launch this app and select Window>Show MIDI Window (Command + 2) from the menu to open it.



2. **Select Network**. Double click it to open the MIDI Network Setup window.




- 3. Add a session by selecting '+' button under My Sessions. Enable the session by clicking the Enabled check box under Session and name it. We are using the default name 'Session 1' in this example.
- 4. **Select 'Anyone'** from the drop down list under 'Who may connect to me:' section.
- 5. **Select this Network Session** from the first drop down list under the 'Live routings' section.

### On the Mac running VoiceQ

 Open MIDI Studio. It is located in Applications/Utilities/Audio MIDI Setup.app. Launch this app and select Window>Show MIDI Window (Command + 2) from the menu to open it.



2. **Select Network**. Double click it to open the MIDI Network Setup window.




- 3. Add a session by selecting '+' button under My Sessions. Enable the session by clicking the Enabled check box under Session. You must give the exactly same name and port used in Step 3. Again, we are using the default name 'Session 1' in this example.
- 4. Now you can see the Mac runs Pro Tools from the Directory list. In our example, its name is Yosemite iMac. **Select the Mac runs Pro Tools** from the list. Connect to it by **clicking the 'Connect' button**.

#### On the Mac running Pro Tools

- 1. Launch Pro Tools application and select Pro Tools>Preferences... from the menu.
- 2. Go to 'Synchronization' tab and check both 'Machine Chases Memory Location' and 'Machine Follows Edit Insertion/Scrub' checkboxes.



- 3. **Select Setup>Peripherals...** from the menu to open the peripherals setup window.
- 4. **Go to 'Synchronization' tab** and **Select the Network port** for both MTC Reader and Generator ports. In this example, it is Network, Session 1.



5. Go to Machine Control tab and enable both Master and Slave: select the IAC Driver under the Master, and give the Master's ID = 120 so as not to cause a conflict when you Set ID of the Slave to 127.



6. Select Setup>MIDI>MIDI Beat Clock... from the Pro Tools main menu to open the MIDI Beat Clock window. Enable MIDI Beat Clock and select the Network port.




7. In the **Transport window or Synchronizations options** via transport, select **'GEN MTC'**. Once activated both PT and VQ will be in sync.




## On the Mac running VoiceQ

Launch VoiceQ and select VoiceQ>Preferences... from VoiceQ
main menu.



- 2. **Enable Output MMC Port** and **select the Network session** by name. In this example it is Session 1.
- 3. Select the **MIDI Chase Icon** in the lower left hand corner of the VoiceQ Project window.



# VoiceQ and Pro Tools are now ready to communicate through your network (RTC-MIDI).

Note: RTC-MIDI protocol used for this configuration is stable in most cases but it does not guarantee zero packet loss. The latency and the possibility of packet loss may vary under your network conditions. Especially when the network is congested, which may cause the latency and packet loss to increase.

## **Dual Machine Setup using MIDI hardware interfaces**


Using separate computers for Pro Tools and VoiceQ with MIDI information sent via MIDI hardware interfaces.

This configuration requires a MIDI hardware interface on both computers, which are connected via a MIDI cable. Many AVID hardware boxes like the M-Box, Digi 001-003, Command 8, Control 24 feature MIDI output ports.

The VoiceQ computer can use any standard USB MIDI interface, with VoiceQ automatically recognizing and chasing incoming MIDI timecode when it is set to online/chase mode.

#### On both Macs running Pro Tools and VoiceQ

- Connect both computers with the MIDI Device using the appropriate MIDI cables. The actual configuration maybe different from the screen shots.
- Open MIDI Studio. It is located in Applications/Utilities/Audio MIDI Setup.app. Launch this app and select Window>Show MIDI Window (Command + 2) from the menu to open it.







3. Check all your MIDI interfaces are shown in the windows of both machines. If not, click `Rescan MIDI' button to rescan MIDI ports. In this example, we used USB MS1x1 MIDI Interface from M-Audio for Pro Tools machine, and USB Uno MIDI Interface from M-Audio for the VoiceQ machine.

## On the Mac running Pro Tools

- 8. Launch Pro Tools application and select Pro Tools>Preferences... from the menu.
- Go to 'Synchronization' tab and check both 'Machine Chases Memory Location' and 'Machine Follows Edit Insertion/Scrub' checkboxes.



- 10. **Select Setup>Peripherals...** from the menu to open the peripherals setup window.
- 11. Go to 'Synchronization' tab and Select the MIDI interface connected to the machine for both MTC Reader and Generator ports.



12. Go to Machine Control tab and enable both Master and Slave, select the IAC Driver under the Master, and give the Master's ID = 120 so as not to cause a conflict when you Set ID of the Slave to 127.



13. Select Setup>MIDI>MIDI Beat Clock... from the Pro Tools main menu to open the MIDI Beat Clock window. Enable MIDI Beat Clock and select the MIDI interface.




14. In the **Transport window or Synchronizations options** via transport, select **'GEN MTC'**. Once activated both PT and VQ will be in sync.




#### On the Mac running VoiceQ

 Launch VoiceQ and select VoiceQ>Preferences... from VoiceQ main menu.



- 2. Enable Output MMC Port and select the MIDI interface connected to the VoiceQ machine.
- 3. Select the **MIDI Chase Icon** in the lower left hand corner of the VoiceQ Project window.



## VoiceQ will now chase the incoming MIDI timecode from Pro Tools through your hardware MIDI interface.

VoiceQ will also scrub the video and scroll text in response to the MIDI machine control. MIDI Beat clock is used for additional synchronization accuracy. The transport controls in VoiceQ can also be used, even when VoiceQ is waiting for external MTC. To have VoiceQ chase incoming MTC from Pro Tools click on the `Chase External Timecode' button in the transport section or use the Quick Key #J.

Please contact <u>VoiceQ Support</u> if you require further information on how to implement any of these configurations.

Thank you

Your VoiceQ Support Team